

## 114209 POS BAG SCAN REMINDER PROMPT

### 1 INTRODUCTION

A new bag scanning reminder has been added to the POS sales and layby screens. This is designed for businesses that are scanning shopping bags onto sales as they are used.

### 2 BENEFITS

- ✓ Better management of bag stock levels at store – less risk of forgetting to add bags to the transactions as they are used

### 3 ASSUMPTIONS/LIMITATIONS

- NO prompt for click and collect or ship from store transactions, limited to Sales and Layby transactions

### 4 SETUP

#### 4.1 REFERENCE GROUP / CODE

A specific reference code will need to be configured against all bag products. I.e. A code that is ONLY used on bag products.

Product Maintenance (Emma@INTL\DOC) Licensed to Bass Internal Customer

File Edit Utilities Reports Help

1 / 1

Fast find

Listing Product BOM & Costing Development Critical Path Sales Pur & Supplier Production Stock Product Audit

Code: BAG BIG Description: BIG BAG

Comments:

Purchased  Stocked  
 Used in production  Concept  
 Produced  Incurs Freight  
 Sold  Extra

No Colours, no Sizes  
 Colours but no Sizes

Product Notes

Ref Bv Colour

Reference	Code
Batch Tp	
Set Type	Whole
Range	WDMENS
Season	Autumn
Prod Grp	STOREBAGS
Stock Typ	Raw Materials
Label	
COigin	
Como Grp	TICKETS


Need a category on the bag products

#### 4.2 SYSTEM PARAMETERS

This feature is activated by a *System parameter*.


Make this setting in > *System parameters* > *Retail POS* > *Prompt to scan shop bag*

- Set the parameter to Yes
- Select the reference group and code used to identify what products are bags



## 5 DESCRIPTION / USAGE

If bags have been added to the sale, when selecting F9 to complete the sale, there will be NO bag reminder. However, if bags haven't been added to the sale, when selecting F9 to complete the sale, a new prompt will display.



- If no bag, click Skip on new screen to proceed to payment with no bag added
- If using a bag, scan bag barcode or search and select bag from the list – this adds the bag to the sale and returns to the main screen
- If using more than one bag, once scan or select first bag, will need to edit bags on main screen before clicking F9 payment to proceed to finish the sale
- Clicking close or Esc key on reminder screen will close the reminder and take back to the main screen but will NOT stop reminder from occurring on next attempt to finish the sale